SWS - Forms in the Maintenance Menu - Workstation Groups

The Workstation Group form allows you to associate a Manitou Workstation with other individual Workstations.

Creating a New Workstation Group in Manitou

Perform the following steps to create a Workstation Group:

1. Navigate to the Maintenance menu, click "Setup", then click "Workstation Groups".

Result: The "Workstation Groups" form displays as shown in the following screenshot:

	View	New	Edit	
Workstation Grou	ups			
Description				
description				

2. Click "Edit".

Result: A new line displays on the form and is denoted by as asterisk as shown in the following screenshot:

	View	New	Edit
3	orkstation Groups		
	Description description		
▶	description		
*			
*			

3. Enter a description for your new Workstation Group and click "Save".

Result: Your new Workstation Group displays in the list as shown in the following screenshot:

Workstation Groups		View	New	Edit
description				
	Ī	Description		
test	_			
	_	test		

Adding an Individual Workstation to Your New Workstation Group

Now that you have created a new Workstation Group, you must add the individual Workstations you want as members of the Workstation Group.

Perform the following steps to add individual Workstations to your new Workstation Group:

1. Navigate to the Maintenance menu, click "Setup", then click "Workstations".

Result: The "Workstations" form displays as shown in the following screenshot:

View		New		Edit				
forkstations	n							
						Workstat	ions	
Description	Client Type	Security Level	Extension	Last Active	WS Grp	Mon. Grp	Attributes	
Pending Workstation	Manitou CS Client	Protected Area		08/23/2013 14:23:27		0		
Pending Workstation	Supervisor Workstation	Protected Area	and the second s	08/06/2013 14:37:38		0		
Pending Workstation	Manitou CS Client	Protected Area	5990003			0		
Pending Workstation	Manitou CS Client	Protected Area	5990003	10/14/2013 08:41:59		0		
Pending Workstation	Supervisor Workstation	Protected Area		10/18/2013 13:57:59		0		
Pending Workstation	Manitou CS Client	Protected Area	5990001	10/18/2013 13:45:15		0		
Pending Workstation	Supervisor Workstation	Protected Area	5990001	10/18/2013 13:50:17		0		
Pending Workstation	Manitou CS Client	Protected Area	5990004	10/17/2013 13:47:54		0		
Pending Workstation	Supervisor Workstation	Protected Area		10/15/2013 12:38:41		0		
Pending Workstation	Manitou CS Client	Protected Area	5990002	08/19/2013 08:29:33		0	8	
Pending Workstation	Supervisor Workstation	Protected Area	5990002	08/16/2013 10:41:43		0		
Pending Workstation	Manitou CS Client	Protected Area		09/13/2013 11:12:10		0		
Pending Workstation	Supervisor Workstation	Protected Area	1			0		

- 2. Click "Edit".
- 3. Select the Workstation you want to add to the Workstation group by click the line on which it displays.
- 4. Click at the right edge of the "WS Grp" column of the line for the Workstation you selected.

Result: The icon for a dropdown menu displays as shown in the following screenshot:

WS Grp		don. Grp	Attributes	
	- 0			
Grp	[escriptio	n	
1	c	description		
2	b	est		

5. Select the Workstation Group to which you want to add the individual Workstation.

Result: The Workstation Group you selected now displays in the "WS Grp" column.

6. Click "Save".