CanCancel

The **CanCancel** programming command Enables an event may be canceled by the Manitou Signal Handler when a canceling event arrives within the timeout period. **This does not function without the Cancel() option on the canceling event code**.

Text				CanCancel(*,*,1,No) 🛛	
CanCancel(*,*,1,No)	×	*	¥	Event	
				Zones *	
				Timeout 1	
				Abort	

Command Parameters

- Event What event cancels the initial alarm.
- Zone Which zone the canceling event exists.
- Timeout Time, in seconds, that the initial event waits for the canceling event.
- Abort Should the Signal Handler change the initial event from an Alarm to a Signal. On = Yes, change to a signal. Off = mark as canceled but do not change the alarm to a signal.